SensorDirect - Upgrade Software

Requirements: .upg File (provided by Surgere)

- 1. Open a browser and enter the device IP/URL:
 - R420 Device URL "http://speedwayr-xx-xx-xx" (xx-xx-xx = last 6 characters of MAC Address)



- 2. Log into reader:
 - Default Username "root"
 - Default Password "impinj"



- 3. To upgrade Software Version:
 - Click Browse (1), locate .upg file:
 - Click Upgrade (2), will take approximately 1 minute to upload:



4. After .upg file is uploaded click *Reboot*, reader takes approximately 1 minute to power cycle:





5. Under Details Application SW Version will show between Hardware Version and Serial Number:

